

HowTo Draw Confidence Regions

Daniel Wegner

June 10, 2011

1 Standard use

In order to draw contour lines representing 90% confidence regions for single EDW events one has to do the following steps:

1. Load the kqpa library.

```
gSystem->Load("$KDATA_ROOT/lib/libkqpa.so");
```

2. Make a KQContourPointList object.

```
KQContourPointList aList("QErecoil");
```

or

```
KQContourPointList aList("IonHeat");
```

3. Fill the list with points ($Q, E_{Recoil}, \sigma_{E_{ion}}, \sigma_{E_{heat}}$) or ($E_{ion}, E_{heat}, \sigma_{E_{ion}}, \sigma_{E_{heat}}$)

- (a) Read an ASCII file in the current working directory with lines of the form

$\langle Q \rangle \langle E_{recoil} \rangle \langle \sigma_{E_{ion}} \rangle \langle \sigma_{E_{heat}} \rangle$ for mode "QErecoil"

$\langle E_{ion} \rangle \langle E_{heat} \rangle \langle \sigma_{E_{ion}} \rangle \langle \sigma_{E_{heat}} \rangle$ for mode "IonHeat"

```
aList.ReadASCIIFile(aFileName);
```

- (b) Add events manually

```
aList.AddPoint(aQvalue, anEnergyRecoil, aSigmaIon, aSigmaHeat);
```

for mode "QErecoil"

```
aList.AddPoint(anEnergyIon, anEnergyHeat, aSigmaIon, aSigmaHeat);
```

for mode "IonHeat"

4. Draw the events in an empty frame

```
aList.Draw(anOption = "");
```

2 Additional features

The default values of the empty frame ($E_{recoil} = 0..1000keV, Q = 0..2$) can be changed with set methods

```
aList.SetQvalueMax(aNewQvalueMin);  
aList.SetQvalueMin(aNewQvalueMin);  
aList.SetEnergyRecoilMax(aNewEnergyRecoilMax);  
aList.SetEnergyRecoilMin(aNewEnergyRecoilMin);
```

The list of points can be cleared by

```
aList.ClearPoints();
```

and single events can be removed by

```
aListRemovePoint(anIndex);
```

In order to find valid indices the size of the list can be retrieved by

```
UInt_t aSize = aList.GetEntries();
```

Also single events can be created and drawn:

```
KQContourPoint anEvent(aQvalue,  
                        anEnergyRecoil,  
                        "QERecoil",  
                        aSigmaIon,  
                        aSigmaHeat,  
                        aSigmaIonHeat,  
                        aConfidenceLevel,  
                        aVoltageBias,  
                        anEpsilon);  
anEvent.Draw(anOption="");
```

or

```
KQContourPoint anEvent(anEnergyIon,  
                        anEnergyHeat,  
                        "IonHeat",  
                        aSigmaIon,  
                        aSigmaHeat,  
                        aSigmaIonHeat,  
                        aConfidenceLevel,  
                        aVoltageBias,  
                        anEpsilon);  
anEvent.Draw(anOption="");
```

In case that there might be changes necessary on the empty frame or the contour function, they can directly be retrieved by

```
TF2* aFunction = aList.GetEmptyFrame();  
TF2* aFunction = anEvent.GetFunction();
```